

MetaTrader 4 Pending Stop Block Plugin

Introduction

The Pending Stop Block plugin is intended to prevent users from requesting a "Buy Stop" and "Sell Stop" order. This plugin will instruct the MetaTrader 4 Platform in rejecting any "Buy Stop" and "Sell Stop" pending orders.

Plugin Installation

To install the plugin, the MetaTrader Server 4 program has to be stopped temporary before copying the MTS-PendingStopBlock.dll file into the "MetaTraderServer4/plugin" in the server root directory.

- 1. To stop the server, click on Start/Administrative Tools/Services.
- 2. Under the Services window, look for MetaTrader Server 4 and click it.
- 3. On the General tab, under Service status, click on the "Stop" button and wait for the MetaTrader server to stop.
- 4. Transfer/Copy the MTS-PendingStopBlock.dll file into the server root directory "plugin" folder.
- 5. Go back to Services window, click "Start" button to start the MetaTrader Server 4 program.

Plugin Configuration

After installation of plugin, it is necessary to configure its settings.

Plugin: MTS-PendingStopBlock 2.05 ?			? ×	
The server plugin is intended for enrichment of the server functionality and represents an external program with remote configuration management.				
Parameters:	Name	Value *		
	groups	*		
Add Delete				
	OK Can	cel		

"MetaTrader" is a trademark of <u>MetaQuotes Software Corp.</u> ©2015 Copyrights reserved for <u>MetaTrader Solutions</u>



Parameter	Description	
symbols	List of symbols to be processed by the Quotes Freeze plugin. The symbols can be listed using templates. For example, USD* - all symbols starting with USD; !SILVER,!GOLD,* - all symbols except for gold and silver.	
groups	Groups processed by the plugin. The groups can be listed using templates. For example, demo* - all demo groups, !real,* - all groups except for the real ones, demoforex-usd, demoforex-jpy - only groups named demoforex-usd and demoforex-jpy, respectively.	

After configuration of the plugin, the MetaTrader Server 4 program has to be restarted for the new configuration to take effect. To restart, look to the top left of the MT Administrator 4 program and click it.

